



SYNTEC
TECHNOLOGY CO.,LTD.

RemoteAPI Operation Manual

Date of export: 2024-09-20
Date of revision: 2022-05-23




SYNTEC


1 System Introduction

1.1 Solution Architecture

The new generation Dipole function separates the man-machine from the core (Figure 1 and Figure 2), allowing users to control the back-end controllers from the front-end applications (e.g., standard man-machines) via the Internet. Users can use this architecture for remote monitoring and remote diagnosis. The front-end application development environment is no longer limited to Windows CE, but can be developed for Windows XP, Windows 7, ... general applications, thus creating unlimited possibilities.



圖一 控制器原有架構




圖二 Dipole 架構

This manual teaches users how to install the CNC simulation software on the front-end Windows user and start using the RemoteCNC One-to-Many API features.


1.2 How to switch on Dipole via HMI controller

The server is positioned in the panel FenuBar: (varies slightly depending on the controller)

1. F6 Parameter Setting → F10 Next Page → F7 Core Server (Fig. 3).
2. F5 Maintenance → F2 Network Settings → F5 Core Server



(圖三 a)



(圖三 b)



(圖三 c)

Use the panel to modify the Dipole settings:



This FenuBar function opens the "Core Server Settings Page" (Figure 4). The following is a description of each parameter:

- "Whether or not to start the server at power on" is whether or not to automatically start the core's Dipole function at power on.
- "Timeout Time" is the time after which the network does not respond and the network connection is disconnected.

After users finish the setting of core Dipole, they can press "F3 Confirm" to save the setting value, or press "F4 Cancel" to restore the setting value. After setting, the Dipole function will be activated automatically next time when power on.

[System Introduction](#)[Instructions for use](#)[Functions](#)

SYNTEC

2 Project Settings

- Please refer to the attached example SyntecRemoteExample and change the project reference Syntec.RemoteCNC.dll (after version 1.2.0 (inclusive) to reference Syntec.OpenCNC.dll).

2.1 Precautions before use

1. Please check the controller version first and check the table below to find the corresponding RemoteAPI version.
2. If you are using RemoteAPI v1, please install MacroDev, the same version of 32 emulation software as the controller.
3. Syntec.OpenCNC.dll, Syntec.RemoteCNC.dll, Syntec.RemoteObj.dll, OCAPI.dll, OCUSER.dll ... etc. must be placed in the same folder as the main application.

2.2 Troubleshooting FAQs

1. The computer firewall needs to be enabled on port 5568, port 5570 for the controller to be connected to the computer.
" Windows environments can be found at Firewall> Advanced Settings> Enter Rule> Add Rule> Ports> TCP > Enter 5568,5570
> Allow All Connections "
 2. Note that computers with two NICs need to have the priority of the NIC that connects to the controller set higher in order to connect properly.
"Windows environment can be found in the Networking and Sharing Centre> Access to change card settings> Pressing F10 will bring up the toolbar> Advanced> Advanced Settings> Adjust the network settings for the card in the connection place "
 3. When using v4 version, if you find that the network is unstable and sends back error messages, please reconnect after 10 seconds.
 4. Using 1.0.12_v1, found that there are missing Syntec.RemoteCNC.dll and Syntec.RemoteObj.dll, please go to the official website to re-grab 1.0.12_v1.
- Note: If there is any error in the above Windows operation,
please find the relevant settings by yourself.
If you are using version 1.2.0, please change reference Syntec.OpenCNC.dll.

2.3 RemoteAPI Version Comparison Table

Controller Version	RemoteAPI Version	note
10.116.54.x later	1.2.1 Later	Remove restrictions on the use of new versions of controllers
10.116.36.x	1.0.12_v4	
10.116.24.x	1.0.12_v3	
10.116.10.x~ 10.116.16.x	1.0.12_v2	
10.116.0.x	1.0.12_v1	Requires installation of MarcoDev

[System Introduction](#)[Instructions for use](#)[Introduction](#)[n to](#)[Functions](#)

SYNTEC

3 Setting the base model & Returning errors

data format

Type Name	space occupied
byte	8-bit
short	16-bit
int	32-bit (computing)
float	32-bit (computing)
string	not limited to

Return error description

return value (short)	error category	instructions
-18	Not supported	The controller does not support this function.
-17	Protocol error (Ethernet version only)	Data from Ethernet Board is incorrect. Contact with the service section or the section in charge.
-16	Socket error (Ethernet version only)	Investigate CNC power supply, Ethernet cable and I/F board.
-15	DLL file error	There is no DLL file for each CNC series corresponding to specified node.
-14	USBEmpty	USB is empty
-13	NoUSB	No USB is pulgin

return value (short)	error category	instructions
-8	Handle number error	Get the library handle number.
-7	Version mismatch between the CNC/PMC and library	The CNC/PMC version does not match that of the library. Replace the library or the CNC/PMC control software.
-6	Abnormal library state	An unanticipated error occurred. Contact with the section in charge.
-2	Reset or stop request	The RESET or STOP button was pressed. Call the termination function.
-1	CNC Busy	Wait until the completion of CNC processing, or retry.
0	Normal termination	Complete the assignment without errors!
1	Error(function is not executed, or not available)	Specific function which must be executed beforehand has not been executed. Otherwise that function is not available.
2	Error(data block length error, error of number of data)	Check and correct the data block length or number of data.
3	Error(data number error)	Check and correct the data number.
4	Error(data attribute error)	Check and correct the data attribute.
5	Error(data error)	Check and correct the data.
6	Error (no option)	There is no corresponding CNC option.
7	Error(write protection)	Write operation is prohibited.
8	Error(memory overflow)	CNC tape memory is overflowed.
9	Error(CNC parameter error)	CNC parameter is set incorrectly.

return value (short)	error category	instructions
10	Error(buffer empty/full)	The buffer is empty or full.
11	Error(path number error)	A path number is incorrect.
12	Error(CNC mode error)	The CNC mode is incorrect.
13	Error(CNC execution rejection)	The execution at the CNC is rejected.Check the condition of execution.
14	Error (Data server error)	Some errors occur at the data server.
15	Error(alarm)	The function cannot be executed due to an alarm in CNC.Remove the cause of alarm.
16	Error(stop)	CNC status is stop or emergency.
17	Error (State of data protection)	Data is protected by the CNC data protection function.
18	Error(Not found Machine ID)	Please Check or not send CNC_CONNECTION command.
19	Error (No out)	Please Check NO.
20	Error(Need to Update RemoteCnc Version)	RemoteAPI version is too old for connected controller, need to update RemoteAPI version.

4 basic category

isUSBExist : Whether there is

Name of the function	bool isUSBExist()			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
return value				

SeriesNo: Controller serial number

Name of the function	short GetSeriesNo(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	szSeriesNo	string	out	Controller serial number or empty string
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

CncOption: Controller software

Name of the function	short GetCncOption(...)
----------------------	-------------------------

citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	szCncOption	string	out	Software options for the controller (separated by spaces)
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

MainBoardPlatformName: Controller main board model number

Name of the function	short GetMainBoardPlatformName(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	szName	string	out	Controller motherboard model number or empty string
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_information: basic related

Name of the function	short READ_information(...)
----------------------	-----------------------------

SYNTEC

citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	Axes	short	out	Number of controllable axes
	CncType	string	out	ex : '18' : Series 180/180i
	MaxAxes	short	out	Maximum number of axes
	Series	string	out	M/T type
	Nc_Ver	string	out	NC Version
	AxisName	string[]	out	Coordinate name of each axis
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_status: status

Name of the function	short READ_status(...)
----------------------	------------------------



SYNTEC

citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	MainProg	string	out	master program filename
	CurProg	string	out	Current implementation slot
	CurSeq	x	out	No support, preset -1
	Mode	string	out	ex: "MDI", "MEM"...
	Status	string	out	ex: "STOP", "START"...
	Alarm	string	out	ex: "ALARM", "*****"
	EMG	string	out	ex: "EMG", "*****"
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			
note	Alarm: when there is an Alarm occurrence, return "ALARM"; when there is no Alarm occurrence, return "*****" EMG: when there is an EMERGENCE STOP occurrence, return "EMG"; when there is no EMERGENCE STOP occurs by echoing "*****"			

READ_position: coordinate

information

Name of the
function

short READ_position(...)

SYNTEC

citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	AxisName	string[]	out	Coordinate name of each axis
	DecPoint	short	out	number of decimal places
	Unit	string[]	out	coordinate unit
	Mach	float[]	out	mechanical coordinates
	Abs	float[]	out	absolute coordinates (geometry)
	Rel	float[]	out	relative coordinates (geometry)
return value				
	Dist	float[]	out	remaining distance

WRITE_relpos. sets the relative coordinate value.

Name of the function	short WRITE_relpos(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	AxisName	string	in	Axis coordinate name
	PosValue	double	in	relative coordinate value
return value				

READ_gcode: G Code

Name of the function	short READ_gcode(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	Gdata	string[]	out	G Code
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_othercode: Other Code (H Code, D Code, T Code, M Code, B Code, F Code, S Code)

Name of the function	short READ_othercode(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	HCode	int	out	H Code
	DCode	int	out	D Code
	TCode	int	out	T Code
	MCode	int	out	M Code
	FCode	int	out	F Code
	SCode	int	out	S Code
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_spindle: Feed rate / RPM

Name of the function	short READ_spindle(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	OvFeed	float	out	Feed Rate Over Ride
	OvSpindle	float	out	Spindle Over Ride
	ActFeed	float	out	Actual feed rate
	ActSpindle	int	out	Actual spindle speed
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_time: time

Name of the function	short READ_time(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	PowerOnTime	int	out	Switch-on time (sec)
	AccumulateCuttingTime	int	out	Cutting time (sec)
	CuttingTimePerCycle	int	out	CYCLE time (sec)
return value	WorkTime	int	out	Processing time (sec)

READ_part_count: number of artefacts

Name of the function	short READ_part_count(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	part_count	int	out	Number of workpieces
	require_part_count	Int	out	Number of workpieces required
	Total_part_count	int	out	Total number of workpieces
return value				

DOWNLOAD_work_record: Download remote processing record file

Name of the function	short DOWNLOAD_work_record (...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	Destination	string	in	Download Destination Path
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

IsDipoleSupported: whether the dipole can be passed within the given timeout period.

slur indicating lega(in music)

Name of the function	bool IsDipoleSupported (...)
----------------------	------------------------------

citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	IPAddr	string	in	Destination IP address
	Timeout	uint	in	Specified timeout time (milliseconds)
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			


READ_MakerConfigInfo: get machine shop

Name of the function	short READ_MakerConfigInfo(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	szModel	string	out	Machine Model
	szMachSN	string	out	Machine serial number
	szDate	string	out	Machine factory date
	szDevSN	string	out	Electronic control serial number
return value	szPhone	string	out	Machine shop phone

WRITE_MakerConfigInfo: Setting machine shop

Name of the function	short WRITE_MakerConfigInfo(...)			
----------------------	----------------------------------	--	--	--

citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	szModel	string	in	Machine Model
	szMachSN	string	in	Machine serial number
	szDate	string	in	Machine factory date
	szDevSN	string	in	Electronic control serial number
return value	szPhone	string	in	Machine shop phone



SYNTEC

5 Alarm Type Function

READ_alm_current: alarms currently occurring

Name of the function	short READ_alm_current(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	IsAlarm	bool	out	Determine if there is an alarm
	AlmMsg	String[]	out	Get current alarm messages
	AlmTime	DateTime[]	out	Get the time of the alarm that is currently occurring
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			
note	<p>The way the alarm arrays are discharged, from new to old.</p> <p>Alarm message format ("Category (Motion)" "Number" "Description")</p>			

READ_alm_history: alert history

Name of the function	short READ_alm_history(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	AlmMsg	string[]	out	Alarm messages
	AlmTime	DateTime[]	out	Alarm time and date
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

note	The way the alarm arrays are discharged, from new to old. Alarm message format ("Category (Motion)" "Number" "Description")			
Name of the function	short READ_alm_history(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	AlmMsg	string[]	out	Alarm messages
	AlmTime	DateTime[]	out	Alarm time and date
	Duration	uint[]	out	Experience time in s seconds
	Clear	bool[]	out	Whether or not it has been lifted
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			
note	<ul style="list-style-type: none">• Only support 10.116.54Q, 10.118.0K, 10.118.11 and above.• The way the alarm arrays are discharged, from new to old.• Alarm message format ("Category (Motion)" "Number" "Description")			



SYNTEC

6 Tool Completion Category Function

READ_offset_title: get the title column of the tool Offset

Name of the function	short READ_offset_title(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	OffsetTitle	string[]	out	title bar
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			
note	range	Return Value Description		models
	Syntec M Series	{ "radius geom", "radius wear", "lenght geom", "lenght wear" }		Mill, Drill, Wood, GlassGrind
	Syntec T Series	{ "wear x", "wear z", "wear a", "length x", "length y", "length a", "tool nose radius", "tool nose r wear", "tool nose" }		Lathe

READ_offset_all: Get all the tool offsets.

Name of the function	short READ_offset_all(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	OffsetData	double[][]	out	supplementary information
return value				

note	OffsetData second array to match the title name (Length Geom...). The information is obtained starting from cutter No. 1.
------	--

READ_offset_scope: Get the tool offset according to the specified scope.

Name of the function	short READ_offset_scope(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	StartNumber	short	in	Starting number (from 1)
	EndNumber	short	in	Termination Number
	OffsetData	double[][]	out	supplementary information
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_offset_single: Get single tool offset

Name of the function	short READ_offset_single(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	ofNumber	short	in	Setting the correction number
	OffsetData	double[]	out	supplementar y information
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

WRITE_offset_all: Write All Tool Offset

Name of the function	short WRITE_offset_all(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	OffsetData	double[][]	in	Setting up supplementary information
return value				
note	Write from the 1st knife until the end of OffsetData.			

WRITE_offset_single: Write Single Tool Offset

Name of the function	short WRITE_offset_single(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	ofNumber	short	in	Setting the correction number
	OffsetData	double[]	in	Setting up supplementary information
return value	0: Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_offset_count: Get the number of tool offset strokes

Name of the function	short READ_offset_count(...)
----------------------	------------------------------

citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	Count	short	out	Number of corrections
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			



SYNTEC

7 Type of workpiece coordinates

READ_work_coord_axis: get the title name of the workpiece coordinates

Name of the function	short READ_work_coord_title(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	WorkCoordTitle	string[]	out	Title Name
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_work_coord_all: Get all the work coordinate information.

Name of the function	short READ_work_coord_all(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	CoordName	string[]	out	term (in a mathematical formula) ex:EXT,G54,G55 ...
	WorkCoord	float[][]	out	Workpiece coordinate data
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			
note	CoordName items such as. EXT,MPGShift, G54, G55, G56, G57, G58, G59 , G54P7, G54P8, G54P100 and so on.			

READ_work_coord_scope: Get the coordinate data of the workpiece according to the specified range.

Name of the function	short READ_work_coord_scope(...)
----------------------	----------------------------------

citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	StartNumber	short	in	Starting number
	EndNumber	short	in	Termination Number
	CoordName	string[]	out	term (in a mathematical formula) ex:EXT,G54,G55 ...
	WorkCoord	float[][]	out	Workpiece coordinate data
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			
note	CoordName items such as.			
	EXT,MPGShift, G54, G55, G56, G57, G58, G59 ,G54P7, G54P8, G54P100 and so on.			
	The following ranges correspond to the coordinate names of the workpiece			
	Name of workpiece		corresponding number	
	EXT		0	
	MPG Shift		1	
	G54		2	
	G55		3	
	G56		4	
	G57		5	
	G58		6	
	G59		7	
G54 P7~P100		8~101		

READ_work_coord_single: get single work coordinate information

Name of the function	short READ_work_coord_single(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	CoordName	string	in	term (in a mathematical formula) ex:EXT,G54,G55 ...
	WorkCoord	float[]	out	Workpiece coordinate data
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

WRITE_work_coord_all: Write all work coordinate data

Name of the function	short WRITE_work_coord_all(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	CoordName	string[]	in	set item ex:EXT,G54,G55 ...
	WorkCoord	float[][]	in	Setting of workpiece coordinate data
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

WRITE_work_coord_single: write single work coordinate information

Name of the function	short WRITE_work_coord_single(...)
----------------------	------------------------------------

citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	CoordName	string	in	set item ex:EXT,G54,G55 ...
	WorkCoord	float[]	in	Setting of workpiece coordinate data
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_work_coord_count: Get the number of work coordinate strokes

Name of the function	short READ_work_coord_count(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	Count	short	out	Number of workpiece coordinate strokes
return value				

SYNTEC

8 Macro Variable Category Functions (Commutative Variables)

READ_macro_all: Get information about all Macro variables (common variables).

Name of the function	short READ_macro_all(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	MacroNumber	int[]	out	Macro number
	MacroData	double[]	out	Information on Macro variables
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_macro_scope: Get Macro (common variable) variable information according to the specified scope.

Name of the function	short READ_macro_scope(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	StartNumber	int	in	Starting number (from 1)
	EndNumber	int	in	Termination Number
	MacroNumber	int[]	out	Macro number
	MacroData	double[]	out	Information on Macro variables
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

WRITE_macro_all: Write information about all Macro variables (common variables)

Name of the function	short WRITE_macro_all(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	MacroNumber	int[]	in	Setting the Macro Number
	MacroData	double[]	in	Setting Macro Variable Information
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_macro_single: Get information about a single Macro variable (common variable).

Name of the function	short READ_macro_single(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	MacroNumber	int	in	Macro number
	MacroData	double	out	Information on Macro variables
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

WRITE_macro_single: Write single Macro variable (common variable) information

Name of the function	short WRITE_macro_single(...)
----------------------	-------------------------------

citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	MacroNumber	int	in	Setting the Macro Number
	MacroData	double	in	Setting Macro Variable Information
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_macro_variable: Get the start and end number of the macro variable (common variable).

Name of the function	short READ_macro_variable(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	Variable	int[][]	out	Macro variable start and end numbers
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			
note	<p>Array declaration: Variable[type][0]:Start Number</p> <p>Variable[type][1]:End Number</p> <p>As:</p> <p>Variable[0][0]:100 Variable[0][1]:199</p> <p>Variable[1][0]:500 Variable[1][1]:599</p>			

9 Machining programme type function

WRITE_nc_main: Specify the processing procedure

Name of the function	short WRITE_nc_main(...)			
Lead type 1	Variable name	type (e.g. blood type)	[in/out]	instructions
	szProgName	string	in	Machining programme name
Lead type 2	Variable name	type (e.g. blood type)	[in/out]	instructions
	szProgName	int	in	Machining programme name
	nCoordID	int	in	Axis Group Number
	nLineNumber	int	in	starting line number
return value				
note	<ul style="list-style-type: none"> Backend controller support version: 10.116.10x or above Backend controller boards 10.116.10x-10.116.16x After specifying the machining programme, the controller mode cannot be changed. The API for Quotient Type 2 is 10.116.54A after the Syntec.RemoteCNC.Win32.dll only provided When using Lead Type 2, refer to this document Multi-Axis Cluster Planning and MST Multi-Channel Applications Manual 			

READ_nc_mem_list: Get the list of internal machining programmes of the machine.

Name of the function	short READ_nc_mem_list(...)
----------------------	-----------------------------

citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	NcList	string[][]	out	Machining programme list
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			
note	<p>Since NC lists vary from manufacturer to manufacturer, the following format is recommended:</p> <p>NcList[][0]:NC Name NcList[][1]:Size (byte) NcList[][2]:Last Write DateTime NcList[][3]: file / directory</p> <p>Note: If there is no processing file, it will still return -1 (CNCBUSY), please note this point.</p>			

UPLOAD_nc_mem: uploads the machining

Name of the function	short UPLOAD_nc_mem(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	Source	string	in	Local full path name
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

DOWNLOAD_nc_mem: Download machining

Name of the function	short UPLOAD_nc_mem(...)
----------------------	--------------------------

citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	Source	string	in	Name of NC file
	Destination	string	in	Local folder path
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

DEL_nc_mem: deletes the machining programme in the controller

Name of the function	short DEL_nc_mem(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	Name	string	in	name (of a thing)
return value				

READ_nc_freespace: remaining space capacity (K)

Name of the function	short READ_nc_freespace(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	FreeSpace	Long	out	Remaining space capacity (K)
return value	0:Completion of the assignment, please refer to Annex for other return error descriptions			

READ_nc_OPLog: get operation logs

Name of the function	short READ_nc_OPLog(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	OPLog	string[]	out	Operation Record
	count	int	in/out	log ratio
return value	0:Completion of the assignment, otherwise please refer to Annex I for a description of the return error			
note	<ol style="list-style-type: none"> 1. count passes in the ratio to be read and passes back the ratio to be read. 2. Passing in a parameter count of 0 returns all operation records. 3. A timeout error occurs, use the SynetcRemoteCNC(ip,timeout) constructor to adjust the timeout up, timeout=0 for none, timeout is in ms. 4. The OPLog returned can be referred to the appendix for the relevant information <p>Note: If there is no Log, it still returns the original array and writes "No Log"</p>			



SYNTEC

10 System Parameter Category Functions

READ_param_max: Get the maximum number of machine parameter

Name of the function	short READ_param_max(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	MaxNumber	int	out	Maximum number of parameters
return value				

READ_param_schema: Get all the parameter information.

Name of the function	short READ_param_schema(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	index	int[]	out	parameter number
	value	int[]	out	parameter value
	context	string[]	out	Parameter description
	bound	string[]	out	Parameter upper and lower limits
	count	int	out	Number of parameters
return value				

READ_param_data: get parameter data

Name of the function	short READ_param_data(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	ParamStart	int	in	Parameter start number
	ParamEnd	int	in	Parameter termination number
	ParmData	int[]	out	Parametric information
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			
note	※ ParamType is set to -1 if the specified parameter number does not exist on the controller or the acquisition fails.			

WRITE_param_single: write single parameter information

Name of the function	short WRITE_param_single(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	ParamID	int	in	parameter number
	val	int	in	The value of the parameter to be written
return value				

11 PLC Category Functions

READ_plc_type: Get the type of PLC address.

Name of the function	short READ_plc_type(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	Addr	string	in	ex:I,O,C,S,A,R
	PlcType	short	out	0:byte 1:short 2:int
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_plc_type2: Get the PLC address type and address size.

Name of the function	short READ_plc_type2(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	Addr	string	in	ex:I,O,C,S,A,R
	PlcType	short	out	0:byte 1:short 2:int
	PlcStart	int	out	address starting number
	PlcEnd	int	out	address ending number
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			
note	The number of I/O depends on the I/O card selected.			

READ_plc_addr: Get the PLC address

information	Name of the function: short READ_plc_addr(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	Addr	string	in	ex:I,O,C,S,A,R
	PlcStart	int	in	address starting value
	PlcEnd	int	in	address termination value
	PlcType	short	out	0:byte 1:short 2:int
	PlcDataB	byte[]	out	Plc information (byte)
	PlcDataS	short[]	out	Plc information (short)
	PlcDataI	int[]	out	Plc Information (int)
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			
note	The obtained value will be put into the array of PlcData(B,S,I), if the number failed to be obtained, the array value will be set to null.			

WRITE_plc_addr: Write PLC address

Name of the function	short WRITE_plc_addr(...)
----------------------	---------------------------

SYNTEC

citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	Addr	string	in	ex:I,C,S,R
	PlcStart	int	in	address starting value
	PlcEnd	int	in	address termination value
	PlcType	short	in	0:byte 1:short 2:int
	PlcDataB	byte[]	in	Plc information (byte)
	PlcDataS	short[]	in	Plc information (short)
	PlcDataI	int[]	in	Plc Information (int)
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_plc_ver: PLC version

Name of the function	short READ_plc_ver(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	Version	string	out	Plc Version Information
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

DOWNLOAD_plc_ladder: download remote ladder file

Name of the function	short DOWNLOAD_plc_ladder (...)
----------------------	---------------------------------

citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	Destination	string	in	Download Destination Path
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_plc_ibit: get PLC I Bit address data

READ_plc_obit: get PLC O Bit address data

READ_plc_cbit: get PLC C Bit address data

READ_plc_sbit: get PLC S Bit address data

READ_plc_abit: get PLC A Bit address data

Bit address information

Name of the function	short READ_plc_ibit(...) short READ_plc_obit(...) short READ_plc_cbit(...) short READ_plc_sbit(...) short READ_plc_cbit(...) short READ_plc_sbit(...) short READ_plc_abit(...) ...) short READ_plc_abit(...)
citation	
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description

READ_plc_register: Get PLC Register address information.

Name of the function	short READ_plc_register(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	PlcStart	int	in	address starting value
	PlcEnd	int	in	address termination value
	PlcData	int[]	out	Plc Information (int)
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_plc_register: Get PLC Register address string information.

Name of the function	short READ_plc_register(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	RAddress	int	in	addresses
	PlcData	string	out	Plc Information(string)
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_plc_timer: Get PLC Timer address information.

Name of the function	short READ_plc_timer(...)
----------------------	---------------------------

citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	PlcStart	int	in	address starting value
	PlcEnd	int	in	address termination value
	PlcTimerValue	int[]	out	Plc Timer Value
	PlcTimerSetting	int[]	out	Plc Timer Setting
	PlcTimerState	short[]	out	Plc Timer Status
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_plc_counter: Get PLC Counter address information.

Name of the function	short READ_plc_timer(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	PlcStart	int	in	address starting value
	PlcEnd	int	in	address termination value
	PlcCounterValue	int[]	out	Plc Counter Value
	PlcCounterSetting	int[]	out	Plc Counter Setting
	PlcCounterState	short[]	out	Plc Counter Status
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

WRITE_plc_ibit: Write PLC I BIT address

data WRITE_plc_cbit: Write PLC C BIT address

data WRITE_plc_sbit: Write PLC S BIT address

data

Name of the function	short WRITE_plc_ibit(...) short WRITE_plc_cbit(...) short WRITE_plc_sbit(...)
citation	
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description

WRITE_plc_register: Write the PLC Register address information.

Name of the function	short WRITE_plc_register(...)			
citation				
	Variable name	type (e.g. blood type)	[in/out]	instructions
	PlcStart	int	in	address starting value
	PlcEnd	int	in	address termination value
	PlcData	int[]	in	Plc Information (int)
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			



SYNTEC

12 system variable function (math.)

READ_state_variable: system state variable information

Name of the function	short READ_state_variable(...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	StateStart	int	in	address starting value
	StateStart	int	in	address termination value
	StateVariable	int[]	out	System status variable information
return value				

READ_debug_variable: Get system diagnostic variable information.

Name of the function	short READ_debug_variable (...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	DebugStart	int	in	address starting value
	DebugEnd	int	in	address termination value
	DebugVariable	int[]	out	Information on system diagnostic variables
return value	0: complete the assignment, otherwise refer to 5-2 Return Error Description NOTE: System diagnostic variables 77 and 78 are specific to the controller, refer to Diagnostic Variable No. 7 if system residual memory information is required.			

READ_system_variable: Get system variable information (#)

Name of the function	short READ_system_variable (...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	SystemID	int	in	Axis group number
	SystemStart	int	in	address starting value
	SystemEnd	int	in	address termination value
	DebugVariable	double[]	out	Information on system variables
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_useTime: System use time

Name of the function	short READ_useTime (...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	Status	String	out	Current machine usage time status
	TimeStart	String	out	Start of use
	TimeExpire	String	out	Use expiry date
	TimeRemain	int	out	Remaining time (hr)

return value	0:Finish the job, please refer to 3-2 Return Error Note: Supported by software version 10.116.24x or above.
--------------	---

Read_remoteTime : Current system time

Name of the function	short READ_remoteTime (...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	remoteTime	DateTime	out	Current machine system time
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

WRITE_remoteDate: Modify system date

Name of the function	short WRITE_remoteDate (...)			
citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	Year	Int	out	sumame Nian
	Month	Int	out	moon
	Day	Int	out	date
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

WRITE_remoteTime: modify system time

Name of the function	short WRITE_remoteTime (...)
----------------------	------------------------------

citation	Variable name	type (e.g. blood type)	[in/out]	instruc tions
	Hour	Int	out	suma me Shi
	Minute	Int	out	ingredi ent
	Second	Int	out	unit of angle or arc equival ent one sixtieth of a degree
return value				
ClearCache: Clear all bu				
Name of the function	sho			
citation	N/A			
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description Note: Clear all buffers (e.g. serial number, motherboard, model, code, etc.) and call the relevant API to get the correct information.			

READ_SSV_GetDeviceInfo

Name of the function	READ_SSV_GetDeviceInfo(...)
----------------------	-------------------------------

The logo for SYNTEC, featuring the company name in a large, bold, sans-serif font. The letters are white with a subtle grey shadow, giving it a 3D appearance. The logo is centered horizontally and occupies a significant portion of the lower half of the page.

citation	Variable name	type (e.g. blood type)	[in/out]	instructions
	nAxisId	int	in	Axis ID
	nFunctionCode	int	in	Which information to fetch enum DevInfoFuncCode { = 0x11. SVPackSoftVer, SVPackSN, SVMotorModel, SVMotorSN, ENCSoftVer, ENCResolution, ENCSensorType, ENCSN. }
	szInfo	string	out	numerical value of information
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_SerialStateVar_ServiceReg

Name of the function	READ_SerialStateVar_ServiceReg(...)
----------------------	-------------------------------------

citi on	Variable name	type (e.g. blood type)	[in/out]	instructions
	nAxisType	int	in	AXIS : 0 SPLCA : 1 ROT : 2
	nDeviceID	int	in	Device ID
	nHandle	int	out	The code for this registration is returned when the registration is successful, and the other Return Error Description. The SerialStateVar function will use the
return value				

READ_SerialStateVar_ServiceUnReg

Name of the function	Variable name	type (e.g. blood type)	[in/out]	instructions
citation	nHandle	int	in	Registration code for the specified update service
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

Name of the function	READ_SerialStateVar_GetCapacity(...)
----------------------	--------------------------------------

citi on	Variable name	type (e.g. blood type)	[in/out]	instructions
	nHandle	int	in	Registration code for the specified update service
	nCapacity	int	out	How many StateVar variables are there

return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description
--------------	--

READ_SerialStateVar_Dump

Name of the function	READ_SerialStateVar_Dump(...)			
citi on	Variable name	type (e.g. blood type)	[in/out]	instructions
	nHandle	int	in	Registration code for the specified update service
	nLength	int	in	How many state-variable specifications of the data structure to be captured
	tStateVarSpecLi st	List<TSerialState VarSpec>	out	Information structure for each state variable specification
	nHexFormat	int	out	Hexadecimal or 10? promotion
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

READ_SerialStateVar_GetValue

Name of the function	READ_SerialStateVar_GetValue(...)			
citi on	Variable name	type (e.g. blood type)	[in/out]	instructions
	nHandle	int	in	Registration code for the specified update service
	nLength	int	in	How many state variables to catch
	SerialStateVarList	List<Int32>	out	Values for each state variable
	nStatus	int	out	in the end FAIL = 0, SUCCESS, BUSY, EXCEPTION.
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description			

SYNTEC

13 Updating Controller Related Functions

UPLOAD_software : Update controller

software UPLOAD_plc_file : Update

controller PLC UPLOAD_param_file :

Name of the function	short Update_software (...) short Update_plc_file (...) short Update_param_file (...)											
citation	<table><tr><td>Variable name</td><td>type (e.g. blood type)</td><td>[in/out]</td><td>instructions</td></tr><tr><td>Source</td><td>String</td><td>out</td><td>pathfile name Software: *\package_xxxx.zip PLC: *\cnc.lad Parameters: *\param.dat</td></tr></table>				Variable name	type (e.g. blood type)	[in/out]	instructions	Source	String	out	pathfile name Software: *\package_xxxx.zip PLC: *\cnc.lad Parameters: *\param.dat
Variable name	type (e.g. blood type)	[in/out]	instructions									
Source	String	out	pathfile name Software: *\package_xxxx.zip PLC: *\cnc.lad Parameters: *\param.dat									
return value	0:Complete the assignment, otherwise refer to 3-2 Return Error Description Note: After updating, the controller must be turned on again before updating is possible											

SYNTEC

14 appendice

The meaning of READ_nc_OPLog.

Name	Data Type	Size	instructions
Event ID	UINT16	2-byte	Pushbuttons, alarms, PLC, time... etc. device
Event Data	UINT16	2-byte	Event values, e.g. PLC-bit values, keypad values, alarm numbers & axes occurring

Record field format

Event Name	Event ID	Event Data
StartUp	0x0002	Null
ShutDown	0x0003	Null
KeyPressed	0x0005	
Date	0x0300~0x03FF 00000011aaaaaaaa a:Year	Current date bbbbbbbbbbcccccccc b:Month c:Date

Event Name	Event ID	Event Data
Time	0x0400~0x04FF 00000100aaaaaaaaa: seconds	Current time bbbbbbbbbbcccccccc b: hours c: minutes
Alarm	0xWC00~0xWCFF zz001100aaaaaaa a: ClassID z:Alarm ID(10~11bit)	Alarm ID bbbbbbcccccccccc b: Object ID c: Alarm ID (0~9bit) Yaskawa Servo Alarms Require 12bit for Full Recording
I-bit off	0x0010	Index
I-bit on	0x0011	Index
O-bit off	0x0012	Index
O-bit on	0x0013	Index
C-bit off	0x0014	Index
C-bit on	0x0015	Index
S-bit off	0x0016	Index
S-bit on	0x0017	Index
R	0x0020	Index
P	0x0021	Index
@	0x0022	Index
L	0x0023	Index

Event Name	Event ID	Event Data
D	0x0024	Index
K	0x0025	Index
ParameterOnChange	0x0030	Param No.
WorkPieceOnChange	0x0031	WorkPieceFrame ID
ToolCompesationOnChange	0x0032	aaaaaaaabbbbcccc a: ToolNo (the first knife) b: AxisNo axial direction c: ToolCompesationType
UserOnChange	0x0033	0x0033XXXX User rights reference R5997 0009: SyntecLogin(R5997=9) 0063: MakerLogin(R5997=99) 0064: AdminLogin(R5997=100) 0065: OtherLogin(R5997=101) 03E7: LogOut(R5997=999) (Unlogged on first boot) Other: XLogin (xxxx decimalised to x)
human-computer activation	0x1002	Null
Human organ closure	0x1003	Null
Action(undefined)	0x1004	The CRC16 value of the action name
Action	0x1005	The mapping value of LogTable